

**Treatment Sequence
Mrs. Celeste Arthur
12-12-2014**

Fabricate implant surgical guide.
Laboratory provisional fabrication.

Prepare teeth #'s 11-15 for provisional bridge.
Place implant in the position of tooth #12.
Extract teeth #'s 13 and 14.
Bone graft extraction sites.
Insert laboratory fabricated provisional bridge from teeth #'s 11-15.

Root canal therapy tooth #20.

Prepare teeth #'s 19 and 20 for full coverage crowns.
Impressions for full coverage crowns on teeth #'s 19 and 20.
Insert laboratory fabricated provisional crowns on teeth #'s 19 and 20.

Place implant in the position of tooth #14.
Extract tooth #15.
Modify provisional bridge.

When healing is complete from extractions, grafting, and implant placement (approximately 4-6 months), we will proceed with:

Finalize impression for crown #11.
Finalize impression for custom implant abutments over implants #'s 12 and 14.
Finalize impression for implant supported bridge 12-14.

Insert crown #11.
Insert custom implant abutments over implants #'s 12 and 14.
Insert implant supported bridge 12-14.

When ready to proceed with right side:

Prepare teeth #'s 3-6 for laboratory fabricated provisional bridge.
Extract tooth #5 and place implant.
Insert laboratory fabricated provisional bridge.

When healing has taken place from the extraction and implant placement (approximately 4-6 months), we will then proceed with:

Extract tooth #3 and place implant.

Modify provisional bridge.

When healing takes place from extraction and implant placement (approximately 4-6 months), we will proceed with:

Finalize impressions for crown on tooth #6.

Finalize impressions for custom implant abutments over implants in the positions of teeth #'s 3 and 5.

Finalize impressions for implant supported bridge teeth #'s 3-5.

Insert crown on tooth #6.

Insert custom implant abutments and bridge teeth #'s 3-5.

Place implants in the position of teeth #'s 28 and 29.

When healing takes place from implant placement (approximately 4-6 months), we will proceed with :

Finalize impressions for custom implant abutments in the positions of teeth #'s 28 and 29.

Finalize impressions for implant supported crowns teeth #'s 28 and 29.

Prepare tooth #30 for a new crown and take impression for new crown.

Insert custom implant abutments over implants in the position of teeth 's 28 and 29.

Insert implant supported crowns over implants teeth #'s 28 and 29.

Insert crown on tooth #30.